



- Open the Eunhasu Web GUI
- Run Squeezelite mode, start Squeezelite mode and open LMS.




- Click the Settings button
 - If the ickStream app was installed, you can see the app in Home → My Apps.
 - Click the Settings button at the bottom right side.




- Install the ickStream App
 - Go to the Plugins tab, and scroll down to the bottom page.
 - Enter the url below in the blank box at the bottom side of the page and click the Apply button.
 - SMS-200: <http://repository.ickstream.com/squeezebox/repository-linuxarmhf.xml>
 - SMS-1000: <http://repository.ickstream.com/squeezebox/repository-linux.xml>
 - Once the new windows appear, click OK to install the ickStream App.
 - Enable 'ickStream' at the Updated plugins available section, and click the Apply button.



- Click 'Reboot Now' and open the LMS again.




- Click the Settings button
 - A. If the ickStream app was installed, you can see the app in Home → My Apps.
 - B. Click the Settings button at the right bottom side.



- Check the ickStream app.
 - You can see the ickStream app in My Apps.
 - Check Settings → Advanced tab , the ickStream settings menu will appear as the image below.

Last update:
2020/01/10
12:23

en:how_to_install_ickstream_app_in_lms https://docs.sotm-audio.com/doku.php?id=en:how_to_install_ickstream_app_in_lms



From:
<https://docs.sotm-audio.com/> - **SOTM docs**

Permanent link:
https://docs.sotm-audio.com/doku.php?id=en:how_to_install_ickstream_app_in_lms

Last update: **2020/01/10 12:23**

